Mission Operations Systems Office (MOSO)

Data Delivery and Operations Program Element

Forecasting And Scheduling Tool for Earth-based Resources (FASTER), Version 2.1

User's Guide

March 1, 1995



Mission Operations Systems Office (MOSO)

Data Delivery and Operations Program Element

Forecasting And Scheduling Tool for Earth-based Resources (FASTER), Version 2.1

# User's Guide

Prepared by M. Brewer	
Approval:	
S. Loyola, System Engineer FASTER Software Development	F. B. Leppla, Group Leader Resource Analysis Team

March 1, 1995



JPL D-12215

# DISTRIBUTION

Allen, B.	525-3670
Altunin, V.	303-402
Arroyo, B.	264-580
Baker, R.	171-260
Borden, C.	601-237
Bouck, A.	525-132A
Bray, T.	264-114
Brown, B.	507-120
Burke, E.	171-260
Fogle, T.	264-580
Golden, K.	301-340
Hampton, E.	600-116
Herrington, E.	264-114
Hodder, J.	303-404
Horton, T.	264-325
Huffman, D.	171-232
Lacey, N.	600-116
Leppla F.	600-116
Loyola, S.	601-237
McClure, J.	301-340
McCluskey, J.	507-120
Ryan, R.	301-340
Slade, M.	238-420
Smith, J.	264-664
Stein, S.	507-120
Strobert, D.	238-420
Tay, P.	507-120
Thompson, W.	525-100A
Wolken, P.	507-120
Woo, H.	301-385
Zendejas, S.	601-237
MOSO Library	171-243
Vellum Files (2)	111-B25

Additional copies of this document are available from the MOSO Library etx. 4-3087 or JPL Vellum Files ext. 4-6222

# **Document Change Log**

Date	Document ID	Pages	Status
3/1/95	M4 MOSO8311-01-00	All	Final
	JPL D-12215		

# **Table of Contents**

1.	Introd	luction			
	1.1	Purpose and Scope 1-1			
	1.2	What's New in FASTER Version 2.0? 1-1			
	1.3	FASTER Philosophy1-2			
	1.4	FASTER: The Tools			
		1.4.1 Scheduling Tools			
		1.4.2 Resource Analysis Tools 1-3			
		1.4.3 Database Management Tools 1-4			
		1.4.4 Miscellaneous Tools 1-4			
	1.5	Conventions			
		1.5.1 Interpreting User Guide Notations			
		1.5.2 Using the Mouse			
		1.5.3 Editing Text			
	1.6	Applicable Documents 1-7			
		1.6.1 JPL Documentation 1-7			
		1.6.2 Commercial Software Documentation 1-8			
2.	Gettir	Getting Started			
	2.1	Hardware and Software Requirements 2-1			
		2.1.1 Hardware			
		2.1.2 Software 2-1			
	2.2	Installing the FASTER Software			
		2.2.1 Setting Up the Workstation 2-2			
		2.2.2 Setting Up the Server			
3.	Editir	Editing Schedules with TEDIT			
	3.1	Loading TEDIT			
	3.2	TEDIT Navigational Aids 3-3			
	3.3	Opening and Saving a Schedule Week			
		3.3.1 Opening a Schedule Week 3-4			
		3.3.2 Saving a Schedule Week			
	3.4	Typing and Revising Schedule Information			
	3.5	Cutting, Copying, and Pasting Schedule Items 3-7			
	3.6	Displaying a Subset of a Schedule 3-8			
	3.7	Forcing SOA or BOT to Remain Constant 3-9			
	3.8	Flagging Conflicts			
	3.9	Searching for Schedule Items			
	3.10	Toggling NIBs, Hards, and Waivers			
4.	Printi	ng Schedules with LineList 4-1			

5.	Identi	fying Tracking Gaps with GAP		
6.		rizing Access to Schedules with SCHEDREL 6-1		
	6.1	Starting SCHEDREL 6-1		
	6.2	Checking Status of Released Schedule Weeks 6-1		
	6.3	Releasing Schedules to the External User Community 6-2		
	6.4	Transferring Schedule Weeks to the DSN		
	6.5	Unreleasing Schedules to the External User Community 6-5		
	6.6	Unreleasing Schedule Weeks from the DSN		
7.	Acces	Accessing Schedules Using RCOMM 7-		
	7.1	Accessing RCOMM 7-1		
	7.2	Listing All Available Plans		
	7.3	Copying the DSN Transfer File		
	7.4	Downloading a File in Raw Data Format		
	7.5	Copying PLANS and DSN Record Format		
	7.6	Copying the Latest Book		
	7.7	Exiting RCOMM 7-12		
8.	Omitte	ed		
9.	Viewi	Viewing Viewperiod Information with VPVIEW 9-		
	9.1	Starting VPVIEW 9-1		
	9.2	Selecting a Viewperiod		
	9.3	Navigating the Viewperiod Display 9-2		
	9.4	Changing the Viewperiod Display Mode 9-3		
	9.5	Changing Viewperiod Fonts 9-3		
	9.6	Printing Viewperiods 9-4		
		9.6.1 Printing the Current Day		
		9.6.2 Printing a Range of Days 9-5		
10.	Forecasting Antenna Contention with FORECAST 10-			
10.	10.1	Starting FORECAST		
	10.2	What's in a FORECAST Workbook?		
	10.3	Navigating the Workbook		
	10.4	Generating a Forecast		
	10.5	Adding Requirement Lines		
	10.6	Removing Requirement Lines		
	10.7	Displaying or Not Displaying Major Events		
	10.8	Saving a Workbook		
	10.9	Printing the Contents of a Forecast Workbook		
	10.10	Making Copies of a Year		
	10.11	Printing Workbook Charts		
	10.11	Sorting the Downtimes Sheet		
	10.12	borung the bownthines sheet 10-2		

11.	Calcu	lating Viewperiod Overlap with OVERLAP	11-1
	11.1	Starting OVERLAP	11-1
	11.2	Entering Viewperiod Settings	11-2
	11.3	Printing the OVERLAP Chart	11-7
12.	Chang	ging FASTER Program Settings with FSTRCTRL	12-1
	12.1	Starting FSTRCTRL	12-1
	12.2	Obtaining Help on FSTRCTRL	12-2
	12.3	Changing the Database Settings	12-2
	12.4	Changing the Defaults	12-5
	12.5	Changing the Mapping Settings	
13.	Maint	taining the RAP Schedule Database with SCHED	13-1
	13.1	Starting SCHED	13-1
	13.2	Loading Weeks into the Schedule Database	13-1
	13.3	Deleting Weeks from the Schedule Database	13-3
	13.4	Archiving Weeks from the Schedule Database	13-4
	13.5	Cataloguing the Schedule Database Contents	13-5
14.	Maint	taining the Viewperiod Database with VPUTIL	14-1
	14.1	Starting VPUTIL	14-1
	14.2	Validating Viewperiod Files	14-1
	14.3	Validating Viewperiod Inputs	14-3
	14.4	Loading Viewperiods into the Viewperiod Database	14-6
	14.5	Deleting Viewperiod Records from the Viewperiod Database	14-9
	14.6	Archiving Viewperiod Records	. 14-10
	14.7	Cataloging the Viewperiod Database	. 14-12
15.	Displa	aying a 12-month Calendar Using DOYCAL	15-1
16.	Maint	taining the Major Events Database with EVENTS	16-1
	16.1	Starting EVENTS	16-2
	16.2	Adding New Events	16-3
	16.3	Deleting Events	16-4
	16.4	Editing Events	16-5
	16.5	Displaying Events	16-6
	16.6	Changing the Font	16-7
17.		nloading Schedule Files Using Netware and WRCOMM	
	17.1	Starting WRCOMM	
	17.2	Listing Available Raw Data Files	
	17.3	Copying Raw Data	
	17.4	Listing Available DSN Transfer Files	
	17.5	Copying the DSN Transfer File	
	17.6	Listing Available Schedule "Books"	
	17.7	Copying the Current Schedule "Book"	17-5

M4 MOSO8311-01-00	JPL D-12215

17.8	Downloading the Triple Space	 17-5

#### 1. Introduction

# 1.1 Purpose and Scope

This document is a comprehensive guide to all the procedures needed to install and run the Forecasting and Scheduling Tool for Earth-based Resources (FASTER) tool suite. It is designed for use by both daily operators and occasional users. It provides detailed step-by-step procedures for using all the FASTER tools, in addition to procedures for maintaining the total FASTER hardware and software environment. This document assumes user familiarity with MS-DOS, MS-Windows, and MS-EXCEL.

The procedures in this document are listed in the order with which they would be used during nominal RAP operations.

#### 1.2 What's New in FASTER Version 2.1

FASTER 2.1 is a minor upgrade to the FASTER tool suite, containing enhancements and closure of open failure reports both from Version 2.0 acceptance testing and subsequent operational use. For further information on the specific Failure Reports (FRs) and Change Requests (CRs) encompassed, please consult the FASTER 2.1 Work Implementation Plan. The following is a brief listing of the new features found in FASTER 2.1:

- C Saving a schedule week to the database will also result in the week's being automatically released to the external users in the raw data format. {TEDIT}
- C An "Auto-Save" feature will allow for periodic saving of the currently open week to the schedule database at user-defined time interval. {TEDIT}
- C Schedule activities that fall outside the scope of the currently edited week will be saved to the appropriate week at the user's discretion. {TEDIT}
- C The NSS viewperiod associated with each schedule activity will be displayted in the LINELIST output. {LINELIST}
- C External users will be able to generate listing of released schedule weeks. {LINELIST}

C A "search & replace" capability will allow for changes to things like configuration codes to span multiple weeks. {SCHED}

- C NSS viewperiods are now capable of being added to the viewperiod database. {VPUTIL}
- C Date information is now displayed in the catalog output. {VPUTIL}
- C After a forecasting run either the results or the infeasible requests worksheet will be immediately displayed. {FORECASTER}

## 1.3 FASTER Philosophy

FASTER is a set of MS-Windows-based applications, working together through shared data to provide forecasting, scheduling, and general data management capabilities for MOSO planning of ground resources.

FASTER is designed around Novell Netware networking and Microsoft Windows multi-tasking capabilities to allow the programs and data to be as widely available and usable as possible. FASTER is designed for centralized data and control (using a Novell file and database server) and decentralized processing.

Each FASTER program provides a single, coherent set of capabilities. Along with MS-Windows multi-tasking capabilities, this approach allows an operator to perform several functions simultaneously. New programs may be added as necessary to provide new required functions.

#### 1.4 FASTER: The Tools

The tools can be divided into four groups:

- Scheduling Tools
- Resource Analysis
- Database Management Tools
- Miscellaneous Tools

Each tool is a stand alone product invoked without reference to any other tool.

Below is a capsule summary of each tool's functionality:

## 1.4.1 Scheduling Tools

TEDIT MS-Windows based schedule editor allowing the

user to edit information in a schedule week.

LINELIST MS-Windows based schedule lister that prints

schedules to either to a printer or ASCII file with

constraint violations optionally checked.

GAP REPORT MS-Windows based program to identify DSN

tracking gaps in user selected schedule week.

SCHEDREL MS-Windows based Schedule release program.

With this program the user controls which schedules are made available to the external

project and DSN users.

RCOMM DOS-based remote communications service

program allowing external users to download released schedule files. This program requires a dedicated communications server, Btrieve for DOS, and the PC-ANYWHERE communications

software.

WRCOMM MS-Windows based remote communications

service program allowing external users to download released schedule files. This program requires a Netware connection to the RAP server.

## 1.4.2 Resource Analysis Tools

VPVIEW MS-Windows based program for viewing

Viewperiod information both on screen and in print format using a Gantt style graph format.

FORECAST MS-Windows/EXCEL based program for

calculation of forecasting information. This program is run as a suite of Microsoft EXCEL

macros.

OVERLAP MS-Windows based program for calculating

Viewperiod overlap information that is input into

Microsoft EXCEL for plotting purposes.

USER SUMMARY MS-Windows/EXCEL based program to

display a summary of user requirements

based on a user-selected year.

EVENTS MS-Windows based major events database.

Major events are used in conjunction with the Forecaster in locating potential periods of high

activity

1.4.3 Database Management Tools

FSTRCTRL MS-Windows based program for modifying

FASTER database file locations and other system

default settings which are stored in the

workstation FASTER.INI file.

SCHED MS-Windows based schedule database

management utility for archiving, deleting, cataloguing, and loading schedule weeks to and

from the master database file.

VPUTIL MS-Windows based database management utility

allowing the archiving, deleting, and cataloguing of Viewperiods in addition to the loading of new and updated Viewperiods into the database.

1.4.4 Miscellaneous Tools

DOYCAL MS-Windows/EXCEL based program generating

a twelve-month calendar with DSN week number and day of year based on a user-selected year.

1.5 Conventions

1.5.1 Interpreting User Guide Notations

(1) Names of keys match the labels shown on most keyboards and appear in capital letters enclosed in angle brackets. For examples, the shift key is <SHIFT>.

(2) A plus (+) sign used between two names of keys indicates you must press both keys one after the other. For example, <ALT+N> means to hold down the Alt key while pressing the N key.

- (3) A comma (,) between two names of keys means that those keys must be pressed sequentially.
- (4) Brackets [] enclose optional parameters for FASTER and DOS commands.
- (5) The world choose is used for carrying out a menu or dialog box command.
  - Click the OK button on the display with the left mouse button.
  - Press the <ENTER> or Carriage Return key on the keyboard.
  - Press the <SPACEBAR> on the keyboard. <sup>1</sup>

(All three keys have the same effect)

- (7) Bold type indicates a button on the display to be "pressed" by pointing to it with the mouse cursor and then clicking the mouse button.
- (8) Words in "quotes" indicate a titled dialog box.
- (9) A numbered list (1,2,3...) (except for those in this section) indicates a procedure of two or more sequential steps.
- (10) <ARROW KEYS> is the collective name for the <UP ARROW>,<DOWN ARROW>, <LEFT ARROW>, and <RIGHT ARROW> keys.

## 1.5.2 Using the Mouse

- (1) Point means to position the point of the mouse pointer on something on the screen.
- (2) Click means press and immediately release the left mouse button without moving the mouse.

<sup>&</sup>lt;sup>1</sup> Only if the **<OK>** button is grayed i.e. inactive

- (3) Double click means to click the left mouse button twice in rapid succession.
- (4) Drag means to press the left mouse button and hold it down while you move the mouse; then release the button.
- (5) Item Selection: To select a program item or cause an action to be performed, position the mouse cursor over the item and click the left mouse button<sup>2</sup>.
- (6) Scrolling: To scroll a window's contents one line at a time, click the left mouse button on the horizontal or vertical arrows at either ends of the scroll bars on the window's right hand side. Each mouse click will scroll the window's contents one line.

Multiple mouse clicks will move the screen contents multiple times.

To scroll a window's contents one page at a time, click the left mouse button between the scroll bars' up or down arrows and the thumb tack (the small square box on the scroll bar). Each mouse click will scroll the window's contents one page full.

To position the window's contents at a specific location, press the left mouse button on the thumb tack and drag it.

# 1.5.3 Editing Text

- (1) To enter text, use the keyboard keys as is done in the DOS environment.
- (2) You can use the arrow keys or the mouse to position where the next character will appear.
- (3) Use the <BACKSPACE> and <DEL> keys to erase characters.
- (4) Use the <ENTER> key to signal the end to keyboard input.
- (5) You can delete data by "selecting" it and pressing the <DELETE> key.

1-6

<sup>&</sup>lt;sup>2</sup> In FASTER, the right mouse button is not used.

## 1.6 Applicable Documents

## 1.6.1 JPL Documentation

This document is consistent with and responsive to the requirements and objectives of the following documents:

- (1) M4 MOSO0477-01-00, FASTER 2.1 Work Implementation Plan, 9 August 1994, JPL D-12659
- (2) M4 MOSO3006-01-01, FASTER Functional Requirements Document, 26 May 1993, JPL D-9962 Change 1
- (3) M4 MOSO3101-03-00, FASTER Software Requirements Document, 1 January1995, JPL D-9963, Rev. B.
- (4) MD MOSO8203-01-00, FASTER Configuration Management Procedures, 5 May 1994, JPL D-9931.
- (5) M4 MOSO0842-01-00, FASTER Release Description Document Version 2.0, 13 October 1994, JPL D-10866.
- (6) M6 MOSO5205-02-00, FASTER System Management Plan, 1 March 1995, JPL D-10464 Rev. A
- (7) M4 MOSO3303-01-01, FASTER Raw Data File Software Interface Specification Change 1, 14 May 1993. JPL D-10484

#### 1.6.2 Commercial Software Documentation

- (1) MS-DOS 5.0/6.0 User's Guide.
- (2) Microsoft Windows 3.1 User's Guide.
- (3) Microsoft Excel 4.0 User's Guide.
- (4) Novell Netware Documentation.
- (5) PC Anywhere User's Guide.
- (6) PROCOMM Plus User's Guide.

# 2. Getting Started

# 2.1 Hardware and Software Requirements

#### 2.1.1 Hardware

The following hardware is needed to run the FASTER software:

#### Server

- • 80386 33-MHz processor with 387 math coprocessor
- •• 16 Mb RAM
- • 600-Mb hard disk
- •• 1 UPS
- • SCSI board/Python Digital audio tape drive system
- • Novell NE-2000 Ethernet board
- • Ethernet cable

#### Workstation

- • 80386 33-MHz processor with 387 math coprocessor
- •• 640 X 480, 16 color graphics; 800 X 600 recommended, 1024 X 768 ideal
- • 8 Mb RAM
- • 150-Mb hard disk
- • Ethernet cable
- • Novell NE-2000 Ethernet board

#### 2.1.2 Software

The following software is needed to support the FASTER software:

#### Workstation

- • MS-DOS Ver. 5.00 or later
- • MS-Windows Ver. 3.1 or later
- • Novell Netware Shell Ver. 3.26
- • Novell Btrieve Data Requester Ver. 5.1
- • PROCOMM PLUS
- • MS-EXCEL Ver. 4.0 or later

#### Server

**CC** Novell Netware Ver. 3.11 or later

CC Novell Btrieve server Ver. 5.1

## 2.2 Installing the FASTER Software

Server setup must be performed before workstation setup; however, since workstation setup is more commonly performed, the workstation setup section is presented first.

# 2.2.1 Setting Up the Workstation

This procedure assumes DOS and Windows have already been installed.

See the respective Netware manuals for installing Netware.

# • Step 1: Set up network access for the workstation and user.

Ensure that the workstation user has a proper account on the JPL-RAP file server where FASTER will reside and that the workstation is set up to properly attach or log in to that server. The AUTOEXEC.BAT file should include command lines that load the appropriate network drivers and log the user into the server. These can be either individual command lines to the AUTOEXEC.BAT or a separate batch file "CALL'd" from the AUTOEXEC.BAT file but physically located elsewhere on the workstation hard disk. For example:

LSL

**NE2000** 

**IPXODI** 

NETX

**F:** (assuming the line "LASTDRIVE=E" is in the CONFIG.SYS file)

**LOGIN JPL-RAP**/ (the user will be prompted for user name and password)

C:

**BREQUEST /D:8192** 

# • Step 2: Create FASTER group and add icons for each FASTER program

To create a FASTER program group in the Windows Program Manager do the following:

- (1) From the MS-Windows Program Manager **File** pull-down menu, select New...
- (2) In the "New Program Object" dialog box, click the **Program Group** radio button, then click **OK**.
- 3) In the "Program Group Description" dialog box, enter the following information:
  - • Description **FASTER**
  - •• Group File (enter nothing)
- (4) Click **OK**.

Windows will display the newly created FASTER group window in the Program Manager's window.

(5) Follow the procedure in the Windows User's Guide (pp. 78-83) for adding programs to a program group. FASTER programs come with pre-built icons that will become visible when they are added to the FASTER group.

The FORECAST icon should contain the command line FORECAST.XLA<sup>3</sup> and the FASTER\EXCEL directory as the working directory.

For all other FASTER tools (i.e., TEDIT, LINELIST, VPVIEW, OVERLAP, FSTRCTRL, VPUTIL, SCHED, and SCHEDREL), the program name should be entered as the command line and the full path of the FASTER EXE directory should be entered in the working

<sup>&</sup>lt;sup>3</sup> Not **.EXE**. The .XLA is an EXCEL macro that will, among other things, call the required .EXE file when needed.


directory. In the case of EVENTS, after EVENTS.EXE, add a space and the letter 'E' (for "edit"). One way of limiting easy access to FASTER tools is through the icons: simply do not add icons for unwanted programs. Another way to do this is to click the **Browse** button and let the Windows Program Manager locate the file for you.

## • Step 3: Install Excel 4.0.

Follow the EXCEL Setup instructions with Excel 4.0 to perform a full installation. For FORECAST to work properly, the File Functions add-ins must be properly installed in EXCEL.

If you are doing a first time EXCEL installation, the file functions add-in will not be present. Unless the file **filefns.xla** is loaded, FORECASTER will not run. To add it to EXCEL, do the following:

(1) From the EXCEL **Options** pull-down menu, select Addins....




The "Add-In Manager" dialog box appears.



(2) If **File Functions** is not listed in the **Add-Ins Installed** list box, click on the **Add...** button.


The "File Open" dialog box appears.




(3) Click on **Filefns.xla** in the files list and click **OK**. EXCEL adds the file **filefns.xla** to its master list.

## • Step 4: Set up FASTER.INI

Copy the FASTER.INI file from the Configuration-Management-provided FASTER installation diskette to the WINDOWS directory of each workstation. The file should be edited, and the entry for Faster Directory should be changed to reflect the workstation's mapping of the root FASTER directory (for example, F:\FASTER). The following three figures show the names to be entered in the dialog boxes accessible from the FASTER Control Panel.







# • Step 5: Set up workstation Btrieve

Each workstation must load the Btrieve workstation requester (BREQUEST.EXE). This Terminate-and-Stay-Resident (TSR) program should be invoked from each workstation's AUTOEXEC.BAT file after the user has successfully logged into the server (since the file should be run from the SYS:PUBLIC directory of the server). The line in the AUTOEXEC.BAT file should be

## **BREQUEST/D:8192**

In addition, each workstation must have access to several MS-Windows Dynamic Link Libraries (DLLs) in order to function properly: **WBTRCALL**, **NWNETAPI**, and **BWCC**. These DLLs are found in the SYS:PUBLIC directory of the server. No copies of WBTRCALL.DLL or WBTRLOCL.DLL should reside on any workstations. If they exist, delete or rename them prior to running FASTER. With ver. 2.0 a new INI file NOVDB.INI must be added to the \WINDOWS subdirectory.

The WIN.INI file located in the workstation's WINDOWS directory should be edited to include the following lines (italicized in this example):

[Btrieve] options=/m:64 /p:4096 /b:16 /f:20 /l:20 /n:12

[brequestDPMI] datalength=8192 tasks=10 local=no chkparms=no

These parameters are needed for proper operation of the BREQUEST.EXE program. In order for the EVENTS tool to operate properly, the "local" parameter must be set to **no**.

The file NOVDB.INI should be added to the workstation \WINDOWS subdirectory. This file is used by the BREQUEST software to configure itself

# • Step 6: Test each program to ensure proper operation.

Run each program according to the relevant sections found in the remainder of this document, and check that no error messages are generated. Most of the FASTER Windows programs have on-line help accessible through the <F1> key or the Help menu entry.

# 2.2.2 Setting Up the Server

This procedure assumes Novell Netware Ver. 3.11 has already been installed on the file server.

## • Step 1: Create directories and copy files.

All the common files required for FASTER are to be kept in a set of subdirectories under one directory on the FASTER file server. The full path of this "root" FASTER directory must be in the FASTER.INI file of each workstation (e.g., F:\FASTER). The required subdirectory names and their contents are:

**EXE** All executable programs.

**DATA** All Btrieve database files and all shared program

information files (.INI) and the following required

subdirectories:

**AMMOS** All AMMOS editor schedules.

**REMOTE** All data files used by the RCOMM program. **DSN** All schedule data files for release to DSN.

**EXCEL** All Excel templates and macros to be used by FASTER.

**HELP** All Windows format help files for FASTER.

## • Step 2: Set up Btrieve server

In order to make the Btrieve server automatically start up when the file server boots up, place the command **BSTART** in the file server's AUTOEXEC.NCF file (using the system options in the INSTALL NLM). There are several parameters that must be set in order for the Btrieve server to operate properly; these parameters are set using the BSETUP NLM. A summary of the parameters and their use follows:

# of open files: 20 This parameter must be set higher than the total number of Btrieve database files that will reside

> and be accessed on the file server (right now only two files).

# of handles: **60**  This parameter must be set higher than the total number of instances of programs that will access Btrieve data. For example, if two users each have two instances (copies) of the text editor running, that is a total of 4 instances and hence each instance will use a handle during the duration of its run.

2048 This number must be set higher than the total # of locks:

number of locks that will be used

simultaneously. Presently, locks are used only by the schedule editor: one per week being

edited.

# of transactions: This parameter is used only if files are created as 0

transactional.

# of files

per transaction: This parameter is used only if files are created as 12

transactional.

Largest compressed

rec size 0 This parameter is used only if compressed

records are used. No compressed records are

currently used in FASTER.

Largest records size 8192

4096 Largest page size

Number of sessions 15

Create files as

transactional NO

**Logging of selected** 

files NO

Below is a listing of the JPL-RAP's current BTRIEVE configuration:

\_\_\_\_\_\_ | NetWare Btrieve Setup V5.15 NetWare 386 Loadable Module

Current Btrieve Configuration

Number of open files: 20

Number of handles: 60

Number of locks: 2048

Number of transactions: 0

Number of files per transaction: 12

Largest compressed record size: 0

Largest record size: 8192

Largest page size: 4096

Number of sessions: 15

Create files as transactional: No

Logging of selected files: No

# • Step 3: Create user groups and accounts

Accounts must be set up so that access to files is given only as needed. User accounts (and hence access) should be categorized into groups (configured according to the discretion of RAP) so that each user account does not have to be tailor made.